

Firebird's fbmgr Superserver Manager

Norman Dunbar

Version 1.8, 24 February 2024

Table of Contents

1. Introduction 2
2. Fbmgr on Linux Systems
2.1. Fbmgr Commands
2.1.1. Getting Help
2.1.2. Starting Up
2.1.3. Shutting Down
2.1.4. Showing Details
2.1.5. Exiting
3. Fguard on Linux Systems
3.1. Fguard Commands
3.1.1. Getting Help
3.1.2. Starting Up
3.1.3. Shutting Down
4. Windows Systems
4.1. Starting The Engine
4.1.1. Using Net Start
4.1.2. Using Instsvc
4.2. Stopping The Engine
4.2.1. Using Net Stop
4.2.2. Using Instsvc
4.3. Querying The Engine
5. Fbmgr Caveats
5.1. Fbmgr is Deprecated at Firebird 2.5
5.2. The Help Command
5.3. Who Owns The Databases?
5.4. What's That Defunct Guardian Process Doing?
5.5. I Can Shut Down But Not Start Up The Engine
5.6. Shut Without Parameters Appears To Be a Bug
Appendix A: Document history.
Appendix B: License notice

Chapter 1. Introduction

Fbmgr is used to start and stop your Firebird Superserver. This is different from starting and stopping a database — as explained in the gfix manual — as the running databases rely on the Firebird service/daemon. This daemon is the Firebird *engine* — without it, nothing will run under Superserver.



If you are using Firebird Classic, this chapter does not apply and it is entirely possible that the executables mentioned in this chapter may not even exist in your installation directory.



If you are using Firebird 2.5 onwards, you will see a message whenever you use fbmgr, telling you that fbmgr has been deprecated. From Firebird 3.0 onwards, this utility is no longer present in Firebird releases. You are advised to use the fbguard utility instead. See the chapter on fbguard for details.

On Windows systems, the engine runs as a service and is slightly different. Windows will be discussed separately in this manual for that reason.

In the remainder of this manual, we will discuss the following:

- Differences between Windows and Linux systems.
- Command-line options for fbmgr.
- Fbmgr commands and their parameters.
- Running fbmgr in interactive or batch modes.
- Some caveats, gotchas and foibles of fbmgr.

Chapter 2. Fbmgr on Linux Systems

On Linux, the Firebird engine is started whenever you carry out an install — from an RPM or via a script — and at system boot time. This means that Firebird is available whenever your system is running once you have Firebird installed.

At boot time, the script /etc/init.d/firebird is executed to start up the Firebird engine on Suse servers, other Linux servers use the script /etc/rc.d/init.d/firebird instead. The same script is executed just before the server shuts down to stop the Firebird engine. The engine runs as the firebird user and not as root.

The script is installed to the location described above, and a symbolic link is created to /usr/sbin/rcfirebird and the script can therefore be called in both ways, whichever you find easiest, but you must be the root user:

tux> /etc/init.d/firebird <parameter>

or

tux> rcfirebird <parameter>

This script can take one of the following parameters:

start

Starts the Firebird engine. If already running, does nothing. The engine is started under the watchful eye of the guardian process (fbguard) and is set to automatically restart if the engine fails for any reason. The engine runs under the firebird user even though you have to be root to run the rcfirebird script.

stop

Stops the Firebird engine. If already stopped, does nothing. It kills the process for the running engine by reading the pidfile (by default /var/run/firebird/firebird.pid). If the process is not running, no error is reported.

status

Checks the current status of the Firebird engine. This command can return a status code (in \$?) as follows:

tux> rcfirebird status ; echo \$?

- 0 the engine is running.
- 1 the engine was not running but the pidfile was found.
- 2 the engine was not running but the lock file was found.
- 3 the engine was not running.

The status parameter is not available on every Linux distribution. You can check if it is available on your installation by running the refirebird command with no parameters:

6

tux> rcfirebird
Usage: /usr/sbin/rcfirebird {start|stop|status|try-restart|restart|
force-reload|reload}

The command will list all the options available for your particular installation.

try-restart

Restarts the Firebird engine but only if it is currently running, otherwise, does nothing.

restart

Stops and restarts the Firebird engine, whether it was running or not.

force-reload

This is exactly the same as the restart command.

reload

Reload is not implemented.

It might be necessary for you to manually shut down the engine from time to time, and to restart it again afterwards. To do this, and assuming that either none of the options to refirebird are suitable or you do not have root privileges, fbmgr is your tool. Fbmgr is, by default, available to all users of the system to execute — however, in order to start and stop the Firebird engine, root or SYSDBA rights are required.

It is noted that the default shell for the firebird user (at least of Suse systems) defaults to /bin/false and so, you cannot log in as the firebird user. This means that you must use rcfirebird to start and stop the engine because if you use fbmgr as root, then all databases created by the engine will be owned by root.

5

In order to allow the firebird user the ability to start and stop the database engine, you need to alter the default shell from /bin/false to something like /bin/bash *and* set a password, while logged in as root, as follows:

tux> usermod --shell /bin/bash firebird
tux> passwd firebird

Fbmgr is a very short shell script which currently—as of version 2.1.3—exports the FIREBIRD environment variable and calls fmbgr.bin passing all supplied parameters over, so fbmgr.bin does all the hard work.

As the two are interchangeable, I shall use the former (and shorter!) fbmgr in the remainder of this chapter.

2.1. Fbmgr Commands

Fbmgr can be run interactively or in batch mode. The commands are identical whichever mode you use and the following section describes the commands and shows examples of each, running in both modes.

To enter interactive mode, simply log in as the firebird user and type the command fbmgr. If /opt/firebird/bin is not on your path, type the command bin/fbmgr instead.



When you log in as the firebird user, the home directory (\$HOME) is set to be /opt/firebird. The bin subdirectory, where all the firebird binaries live, is immediately beneath \$HOME.

2.1.1. Getting Help

To see a list of all the commands — except, for some reason, the start command — run fbmgr and pass the -help command (in batch mode) or type help at the prompt in interactive mode. The resulting output is the same regardless, including the grammatical error "... also be used as an option switches ...":

```
tux> fbmgr -help
Usage:
                fbmgr -command [-option [parameter]]
                fbmgr<RETURN>
οг
                FBMGR> command [-option [parameter]]
                shut [-now]
                                         shutdown server
                show
                                         show host and user
                user <user name>
                                         set user name
                password <password>
                                         set DBA password
                pidfile <filename>
                                         file to save fbserver's PID
                help
                                         prints help text
                quit
                                         quit prompt mode
Command switches 'user' and 'password' can also be used
as an option switches for commands like start or shut.
For example, to shutdown server you can:
fbmgr -shut -password <password>
οг
fbmgr<RETURN>
FBMGR> shut -password <password>
οг
fbmgr<RETURN>
```

FBMGR> password <password> FBMGR> shut



When using this option under Firebird 2.5, an additional line is printed at the beginning of the output advising you that "fbmgr is deprecated and will be removed soon".

2.1.2. Starting Up

When the Firebird engine is started, it normally runs under the watchful eyes of the guardian process — fbguard. The guardian will restart the engine any time it determines that the engine has crashed and in doing so, will hopefully reduce the downtime that the users may suffer as a result of a crashed engine.

It is possible, however, to force the engine to be started up and the guardian will allow it to stay down if it detects a crash. Fbmgr allows the DBA or System Administrator to decide which of the two startup methods will be used.

Start And Stay Running

At system boot time, the engine is started in the mode that allows the guardian to restart it in the event of a crash. To perform this task manually using fbmgr you would carry out one of the following:

tux> fbmgr -start -forever
server has been successfully started

Or, in interactive mode:

tux> fbmgr
FBMGR> start -forever
server has been successfully started

If you are logged in as a *privileged user* then you don't need to specify a -user as these login accounts default to SYSDBA when fbmgr is run. If you log in as any other user, even supplying a user name will not be enough to allow you to restart a closed database engine.

A privileged user is one that the Firebird engine considers to be privileged enough to automatically be given SYSDBA rights. This means that it can start and stop the engine without being required to authenticate as SYSDBA. At present there are four login names that are assumed to be privileged, these are:

- root
 - firebird
 - interbase

• interbas (without the 'e')

The start command defaults to -forever if nothing is specified.

tux> fbmgr -start
server has been successfully started

Start And Stop Running

Under normal circumstances you would wish for the database engine to remain running as long as possible. At other times, however, you may wish for any crashes to be investigated prior to restarting the engine. This is possible using fbmgr as the following shows:

tux> fbmgr -start -once

Or, running interactively:

tux> fbmgr FBMGR> start -once

2.1.3. Shutting Down

Shutting down the engine stops the guardian process from restarting it. If this was not the case, it would be very difficult to actually stop the Firebird engine!



Any user who has logged on to the database server and who is armed with the SYSDBA password, can close the engine down. This is a slight inconsistency as only the privileged users can start the engine.

If you are logged in as a privileged user, you do not need to supply a user name to shut down the engine, you are only required to supply the SYSDBA password.

```
tux> fbmgr -shut -password secret
server shutdown completed
```

You are required to supply a user name if you log in as your own account.

```
tux> fbmgr -shut -password secret
no permissions to perform operation
```

```
tux> fbmgr -shut -user sysdba -password secret
server shutdown completed
```

2.1.4. Showing Details

The show command displays the name of the server that you are running on and details of the user you are currently using. If you are running fbmgr as a privileged user, then the user will be SYSDBA unless you specified a different one with the -user parameter.

tux> fbmgr -show Host: localhost User: SYSDBA

You can supply a different user name on the command line if desired:

```
tux> fbmgr -show -username norman
Host: localhost
User: NORMAN
```

In interactive mode, the process is almost identical:

tux> fbmgr FBMGR> show

Host: localhost User: SYSDBA

Or, using a different user name:

```
tux> fbmgr -user norman
FBMGR> show
Host: localhost
User: NORMAN
```

It appears that the show command always displays the host name as localhost while you are logged onto that server. It is unfortunate that the show command doesn't show any details about the running (or otherwise) Firebird engine. You can find this out as follows:

tux> ps -et grep -1 tire[b]ird					
firebird	3752	1	0 14:13 ?	00:00:00 /opt/firebird/bin/fbguard -o	
firebird	3753	3752	0 14:13 ?	00:00:00 /opt/firebird/bin/fbserver	

Look closely at the process details for the guardian, you can see a -o parameter. This indicates that the engine is running and is in -once mode. If it crashes at any time, it will not be restarted by the guardian. In -forever mode, the parameter is -f.

If you don't see either the guardian or the server processes, then you can assume that the (Superserver) engine is not running.

When using grep to filter out the interesting processes from a call to ps -ef, for example, using a character class for one single character prevents the grep process itself from being listed. The following two grep commands produce identical results but using the character class in the first saves having to call grep -v grep to filter out the unwanted grep process.

```
\mathbf{O}
```

```
ps -ef | grep -i fire[b]ird
ps -ef | grep -i firebird | grep -v grep
```

2.1.5. Exiting

The quit command gets you out of an interactive session. There is no quit command for batch mode.

Chapter 3. Fguard on Linux Systems

From Firebird 2.5 onwards the use of fbmgr is deprecated and from Firebird 3.0, it will be removed. The fbguard utility, which was actually used by fbmgr, should be used instead. The system start and stop scripts, as described in the previous chapter, use fbguard to start and stop the Firebird engine at system startup and shutdown.

3.1. Fguard Commands



For best results and security, you are advised to *always* start and stop the Firebird engine using the default scripts /etc/init.d/firebird or the alias rcfirebird. These scripts carry out various checks to ensure that the engine runs as the correct user, makes sure that the guardian process watches over the engine and so on. Running fbguard on its own makes no such checks and *can* lead to databases becoming unavailable due to being owned by root, for example—because this command always runs the Firebird engine as the root user.

Fguard cannot be run interactively, you must supply the required commands on the command line when executing fbguard. Fbguard can be run as the firebird user, for example, but will always cause the engine itself to run as root. This may be a cause of serious concern for system administrators. If you create any databases while the engine is running as root then those databases will be owned by root and you will *not* be able to access it at some future point when the engine runs — correctly — as the firebird user.

If you always use the `/etc/init.d.firebird` (or rcfirebird) command to start and stop the engine, it will *always* run as the firebird user, regardless of which user you actually run the command as.



You cannot mix and match the various methods of starting and stopping the engine. If you use fbguard to start the engine, you need to kill the fbserver process to stop it. If you use /etc/init.d/firebird (or rcfirebird) to start the engine, you *must* use the corresponding stop script. You cannot shut down the engine with rcfirebird stop, for example, if you started it with fbguard.

3.1.1. Getting Help

To see a list of all the commands run fbguard passing the -help command. The resulting output is as follows:

```
tux> cd /opt/firebird/bin
tux> ./fbguard -help
Usage: fbguard [-signore|-onetime|-forever (default)][-daemon][-pidfile filename]
```

The use of the -daemon option forces the engine to run as a daemon. If you run the fbguard command to start the engine from a terminal session, your terminal will hang.

By default, fbguard will use its own default location to store the file that holds the process id of the

running Firebird engine. You may tell it to use a specific pidfile, if you wish, by specifying the -pidfile option. The default is /var/run/firebird/default.pid.



In Firebird 2.50 and 2.5.1, on the OpenSuse platform, the default pidfile is named /var/run/firebird/.pid because of a bug in the /etc/init.d/firebird script where the variable INSTANCE is not defined. It should be defined with a value of default.

3.1.2. Starting Up

When the Firebird engine is started at system boot or by the /etc/init.d/firebird script, it runs under the watchful eyes of the guardian process. The guardian will restart the engine any time it determines that the engine has crashed and in doing so, will hopefully reduce the downtime that the users may suffer as a result of a crashed engine. It is possible, however, to force the engine to be started up and the guardian will allow it to stay down if it detects a crash.

As mentioned above, regardless of the user you are logged in as when you execute the fbguard command, the engine always runs as the root user.

Regardless of the start mode chosen, the -signore option can be used to indicate that startup errors are to be ignored, and fbguard is to continue to attempt to startup the engine. Startup errors include problems such as port 3050 already being used, etc. Normally, on a startup error fbguard will make no further attempt to start the engine.

Start And Stay Running

At system boot time, the engine is started in the mode that allows the guardian to restart it in the event of a crash. To perform this task manually using fbguard you would carry out the following process:

tux> fguard -forever -daemon

The command defaults to -forever if nothing is specified.

tux> fguard -daemon

Start And Stop Running

Under normal circumstances you would wish for the database engine to remain running as long as possible. At other times, however, you may wish for any crashes to be investigated prior to restarting the engine. This is possible using fbguard as the following shows:

tux> fguard -onetime -daemon

3.1.3. Shutting Down

There is no fbguard command line option that shuts down the running Firebird engine. To do so

requires that you kill the running process as root.

00:00:00 /opt/firebird/bin/fbserver

```
tux> kill 11556
```

```
tux> ps -ef| grep -i fire[b]ird
## No output shown ##
```

The fbserver process is always listed as running from /opt/firebird as per the output from the various grep commands above. The fbguard process, on the other hand, doesn't show the full path unless it was started using the full path, as follows:

```
tux> cd /opt/firebird/bin
tux> ./fbguard -forever -daemon
tux> ps -ef | grep -i fire[b]ird
        11794 11793 0 12:32 ?
                                       00:00:00
root
/opt/firebird/bin/fbserver
tux> ps -ef|grep -i fb[g]uard
        11793
                  1 0 12:32 ?
                                      00:00:00 ./fbguard -forever
root
-daemon
tux> kill 11794
tux> /opt/firebird/bin/fbguard -forever -daemon
tux> ps -ef | grep -i fire[b]ird
                  1 0 12:34 ?
root
        11838
                                       00:00:00
/opt/firebird/bin/fbguard -forever -daemon
        11839 11838 0 12:34 ?
                                      00:00:00
root
/opt/firebird/bin/fbserver
```

Chapter 4. Windows Systems

On Windows 2000/2003, Vista and NT systems as well as the non-home versions of XP, the Firebird engine runs as a service as does the Firebird Guardian. Both of these run under the local system user account. For best results and stability, you are advised to keep Firebird running as a service rather than as an application.

After installation, these two services are defined to be started and stopped automatically on server boot and shutdown. If you wish to control when the services are started and stopped, use *Control Panel* to change their properties to manual.

On Windows ME, 95, 98 and XP Home, the engine runs as an application as does the guardian. In this case, an icon will be seen in the system tray and you can carry out manual maintenance by right clicking on the icon.



The remainder of this section assumes that you have the Firebird engine and the guardian running as services. All the engine commands are accessed via a right-click on the guardian icon in the system tray when running as an application.

On Windows, the guardian process is the file fbguard.exe and the engine itself is the file fbserver.exe.

Normally the instsvc command is used to install or remove services. It can also be used to start and stop services that already exist. When discussing the instsvc command below, it will be used only to start and stop services rather than installing and removing them.

4.1. Starting The Engine

When you start the guardian service on Windows, it will automatically bring up the database engine without you needing to physically start it too.

4.1.1. Using Net Start

Provided you know the exact service name, you can use the net commands to start (and stop) the guardian and database engine. Up until Firebird 2.0, the service name was simply "FirebirdServer". From Version 2.1 onwards, there can be many different services running. In this section, only the default services for Firebird 2.x will be discussed and these are "Firebird Guardian - DefaultInstance" and "Firebird Server - DefaultInstance". As there are spaces in the names, double quotes are required to prevent errors.

```
C:\>net start "firebird guardian - defaultinstance"
The Firebird Guardian - DefaultInstance service is starting.
The Firebird Guardian - DefaultInstance service was started successfully.
```

4.1.2. Using Instsvc

As you can see from the above, under Firebird 2.x, the service names are a bit unwieldy. It is easier to use instsvc to start the services as you do not need to know the default service names.

```
C:\>instsvc start
Service "Firebird Guardian - DefaultInstance" successfully started.
```

4.2. Stopping The Engine

When you stop the guardian service on Windows, it will automatically bring down the database engine without you being required to stop it too.

4.2.1. Using Net Stop

As with starting the services, in order to use net stop to bring the guardian and engine down, you need to know the exact service name (for the guardian) and enclose it in quotes if there are spaces in the name.

```
C:\>net stop "firebird guardian - defaultinstance"
The Firebird Guardian - DefaultInstance service is stopping.
The Firebird Guardian - DefaultInstance service was stopped successfully.
```

4.2.2. Using Instsvc

As with starting the default services, stopping them is far easier using instsvc.

```
C:\>instsvc stop
Service "Firebird Guardian - DefaultInstance" successfully stopped.
```

4.3. Querying The Engine

It is possible to query the services running on the server to check whether the Firebird services are running or not. Once again, the instsvc command is used:

```
C:\>instsvc q
Firebird Guardian - DefaultInstance IS installed.
  Status : stopped
  Path : C:\Program Files\Firebird\Firebird_2_0\bin\fbguard.exe -s
  Startup : manual
  Run as : LocalSystem
Firebird Server - DefaultInstance IS installed.
  Status : stopped
```

```
Path : C:\Program Files\Firebird\Firebird_2_0\bin\fbserver.exe -s
Startup : manual
Run as : LocalSystem
```

It can be seen from the above, that there are two services installed on this server, but none of them are currently running. Other details are displayed such as whether or not these services are started automatically on reboot—in the example above, this is not the case—and the user account (LocalSystem) under which the services will be run, when they are started.

This command is very useful as it displays the two service names—once you have that information, you may use the net stop or net start commands to bring the database down and to restart it.

Chapter 5. Fbmgr Caveats

The following caveats are all specific to the Linux (and by assumption, other Unix systems) and do not apply to Windows versions of Firebird. The reason is simple, Windows doesn't have an fbmgr application as it uses the instsvc command instead.

5.1. Fbmgr is Deprecated at Firebird 2.5

The biggest drawback to the fbmgr utility is the fact that it is deprecated from Firebird 2.5 onwards and will be removed altogether from Firebird 3.0. You are advised to use fbguard instead.

5.2. The Help Command

The help command, as described above, doesn't mention that fact that there is a start command. There is a very brief mention of the start command, but no text explains its use, unlike the other commands which are described.

5.3. Who Owns The Databases?

While not an error as such, this is something that you should be aware of. When the server boots, it starts the Firebird engine and runs it as the user firebird. By default, the firebird has no interactive shell — it defaults to /bin/false — and so you cannot log in to, or su to, the firebird user to manually run a command.

This means that, unless you change the firebird user's default shell as described above, you will have to carry out any manual restarts etc of the engine as the root user — although you can shut it down as any user provided you have the SYSDBA password.

If you do restart the engine as root, then it will now be running as root. While existing databases — owned by the firebird user — will happily be read from and written to by root, any new databases created will be owned by root. Everything will work fine for a while but after the server is next rebooted, these new databases will then fail to be accessible as the engine is now running as the firebird user again and that user has no permissions to access the databases owned by root.

You are therefore advised to always start and stop the server either:

- as root, using the refirebird command; or
- as firebird, using fbmgr.

but never, ever, as root using fbmgr. If you follow the above instructions, all your databases will be owned by the firebird user.

5.4. What's That Defunct Guardian Process Doing?

If you run fbmgr and shut down the database engine, the fbserver process vanishes from the list of processes running under the firebird user. However, a ps -ef|grep -i fir[e]bird command will

show the following:

```
tux> ps -ef|grep -i fir[e]bird
firebird 29978 29844 0 15:57 pts/0 00:00:00 /opt/firebird/bin/fbmgr.bin
firebird 29979 29978 0 15:57 ? 00:00:00 [fbguard] <defunct>
root 29992 29955 0 15:57 pts/1 00:00:00 grep -i fire
```

The guardian process, fbguard, doesn't vanish until you exit from fbmgr. This again is not a major problem, but knowing that all you have to do is exit from fbmgr to make it vanish is helpful.

5.5. I Can Shut Down But Not Start Up The Engine

If you log in to the server as a privileged user and have the SYSDBA's password, you can shut down and start up the engine with no problems. If, on the other hand, you log in as any other user and try to use fbmgr to stop and start the Firebird engine, you will find that you can stop it with no problems but you will not be allowed to restart it. Only privileged users can start the engine. The following shows the problem.

```
tux> # Shutdown Firebird engine as user 'norman'.
tux> fbmgr -shut -password secret
no permissions to perform operation
tux> fbmgr -shut -user sysdba -password secret
server shutdown completed
tux> # Try to restart the Firebird engine as user 'norman'.
tux> fbmgr -start
no permissions to perform operation
tux> fbmgr -start -password secret
no permissions to perform operation
tux> fbmgr -start -user sysdba -password secret
no permissions to perform operation
tux> # Give up and restart the engine as 'firebird'.
tux> su - firebird
tux> bin/fbmgr -start
server has been successfully started
```

It can be seen from the above that a normal user armed with the SYSDBA user name and password can stop the Firebird engine but is completely unable to restart it afterwards.

The reason why this is the case is quite simple. Until the firebird engine is started, there is no way to check that the password supplied for the SYSDBA user is actually correct. Because of this, logging

in as a privileged user assumes SYSDBA privileges and allows you to start the engine.

5.6. Shut Without Parameters Appears To Be a Bug

Running fbmgr's -shut command with no user or password gives the following cryptic output:

tux> fbmgr -shut Invalid clumplet buffer structure: buffer end before end of clumplet no length component can not attach to server

The same result is obtained even with a user name supplied:

tux> fbmgr -shut -user sysdba Invalid clumplet buffer structure: buffer end before end of clumplet no length component can not attach to server

Appendix A: Document history

The exact file history is recorded in the firebird-documentation git repository; see https://github.com/FirebirdSQL/firebird-documentation

Revision History

1.0	29 Sep 2009	ND	Created as a chapter in the Command Line Utilities manual.
1.1	11 Oct 2009	ND	Some screen output wrapped as it extended out of the page in the generated pdf.
1.2	20 Oct 2009	ND	Replaced all references to "root or firebird" account names with "privileged users" as there are more than just these two accounts. Converted to a stand alone manual.
1.3	21 Oct 2009	ND	A few spelling mistakes corrected.
1.4	26 Oct 2009	ND	The status option to the refirebird command is not available on all Linux distros. Text amended to warn the reader of this discrepancy.
1.5	11 Oct 2011	ND	Spelling corrections.
1.6	13 Oct 2011	ND	Updated to mention that fbmgr is deprecated from Firebird 2.5 onwards, and removed altogether from Firebird 3.0.
			Added a chapter on using fbguard.
1.7	17 Jun 2020	M R	Conversion to AsciiDoc, minor copy-editing

Appendix B: License notice

The contents of this Documentation are subject to the Public Documentation License Version 1.0 (the "License"); you may only use this Documentation if you comply with the terms of this License. Copies of the License are available at https://www.firebirdsql.org/pdfmanual/pdl.pdf (PDF) and https://www.firebirdsql.org/manual/pdl.html (HTML).

The Original Documentation is titled *Firebird Superserver Manager*.

The Initial Writer of the Original Documentation is: Norman Dunbar.

Copyright © 2004–2011. All Rights Reserved. Initial Writer contact: NormanDunbar at users dot sourceforge dot net.